

# X Display Manager

## XDMCP Server

### gdm

#### Ubuntu

/etc/gdm/gdm.conf-custom :

```
[xdmcp]
Enable=true
```

```
/etc/init.d/gdm restart
```

#### Debian 5.0

/etc/gdm/gdm.conf :

```
[xdmcp]
Enable=true
```

```
/etc/init.d/gdm restart
```

#### Debian 6.0

/etc/gdm3/daemon.conf :

```
[xdmcp]
Enable=true
```

```
/etc/init.d/gdm3 restart
```

#### Centos / RedHat

```
gdmsetup
```

oder /etc/gdm/custom.conf :

```
[xdmcp]
Enable=true
```

```
pkill gdm-binary
```

### Begrüßungsmeldung ändern

```
gdmsetup
```

oder /etc/gdm/custom.conf :

```
[greeter]
DefaultWelcome=false
Welcome=Hallo %n
```

```
pkill gdm-binary
```

## kdm

### Debian

/etc/kde3/kdm/kdmrc :

```
[xdmcp]
Enable=true
```

/etc/kde3/kdm/Xaccess :

```
*                #any host can get a login window
```

```
/etc/init.d/kdm restart
```

### Begrüßungsmeldung ändern

/etc/default/kdm.d/10\_desktop-base : ( Debian 5.0 )

```
USETHEME="false"
```

/etc/kde3/kdm/kdmrc :

```
[X-*-Greeter]
GreetString=Willkommen auf %n
```

```
/etc/init.d/kdm restart
```

## SuSE

```
/etc/sysconfig/displaymanager :
```

```
DISPLAYMANAGER_REMOTE_ACCESS="yes"
```

```
SuSEconfig
```

SuSEconfig ändert nun die Datei /etc/opt/kde3/share/config/kdm/kdmrc: ( bis kde3 )

```
[Xdmcp]
Enable=true
```

```
/etc/init.d/xdm reload
```

SuSEconfig ändert nun die Datei /etc/X11/xdm/xdm-config: ( openSuSE 11.4 )

```
!DisplayManager.requestPort: 0
```

```
/etc/init.d/xdm reload
```

## Dokumentation

```
konqueror help:/kdm
```

## xdm

```
/etc/X11/xdm/xdm-config :
```

```
! DisplayManager.requestPort: 0
```

```
/etc/X11/xdm/Xaccess :
```

```
*                                #any host can get a login window
```

## XDMCP Client

### X als Terminal

```
X -query <server> :1 vt8 &
```

### mit init automatisch starten

```
/etc/inittab :
```

```
xx:5:respawn:/usr/bin/X -query notebook17 :1
```

## Alternativ mit Xephyr

Pakete:

- openSuSE (11.1): xorg-x11-server-extra
- CentOS (5.3): xorg-x11-server-Xephyr
- Debian (5.0): xserver-xephyr

```
Xephyr -query notebook17 :1 &
```

## Display-Manager auswählen

### CentOS

/etc/sysconfig/desktop :

```
DISPLAYMANAGER=XDM
```

### SuSE

/etc/sysconfig/displaymanager :

```
DISPLAYMANAGER=XDM
```

### Debian

```
dpkg-reconfigure kdm
```

oder

/etc/X11/default-display-manager :

```
/usr/bin/kdm -query <server> :1 vt8
```

From:  
<https://wiki.lab.linuxhotel.de/> - **Linuxhotel Wiki**

Permanent link:  
[https://wiki.lab.linuxhotel.de/doku.php/admin\\_grundlagen:xdm?rev=1325768816](https://wiki.lab.linuxhotel.de/doku.php/admin_grundlagen:xdm?rev=1325768816)

Last update: **2012/01/05 13:06**

