

X Display Manager

XDMCP Server

gdm

Ubuntu

/etc/gdm/gdm.conf-custom :

```
[xdmcp]
Enable=true
```

```
/etc/init.d/gdm restart
```

Debian 5.0

/etc/gdm/gdm.conf :

```
[xdmcp]
Enable=true
```

```
/etc/init.d/gdm restart
```

Debian 6.0

/etc/gdm3/daemon.conf :

```
[xdmcp]
Enable=true
```

```
/etc/init.d/gdm3 restart
```

Centos / RedHat

```
gdmsetup
```

oder /etc/gdm/custom.conf :

```
[xdmcp]
Enable=true
```

```
pkill gdm-binary
```

Begrüßungsmeldung ändern

```
gdmsetup
```

oder /etc/gdm/custom.conf :

```
[greeter]
DefaultWelcome=false
Welcome=Hallo %n
```

```
pkill gdm-binary
```

kdm

Debian

/etc/kde3/kdm/kdmrc :

```
[xdmcp]
Enable=true
```

/etc/kde3/kdm/Xaccess :

```
*                #any host can get a login window
```

```
/etc/init.d/kdm restart
```

Begrüßungsmeldung ändern

/etc/default/kdm.d/10_desktop-base : (Debian 5.0)

```
USETHEME="false"
```

/etc/kde3/kdm/kdmrc :

```
[X-*-Greeter]
GreetString=Willkommen auf %n
```

```
/etc/init.d/kdm restart
```

SuSE 12.1

```
/etc/sysconfig/displaymanager :
```

```
DISPLAYMANAGER_REMOTE_ACCESS="yes"
```

```
service xdm reload
```

1)

Dokumentation

```
konqueror help:/kdm
```

xdm

SUSEconfig ändert nun die Datei /etc/X11/xdm/xdm-config: (openSuSE 11.4)

```
/etc/X11/xdm/xdm-config :
```

```
! DisplayManager.requestPort: 0
```

```
/etc/X11/xdm/Xaccess :
```

```
* #any host can get a login window
```

XDMCP Client

X als Terminal

```
X -query <server> :1 vt8 &
```

mit init automatisch starten

```
/etc/inittab :
```

```
xx:5:respawn:/usr/bin/X -query notebook17 :1
```

```
init q
```

Im Fenster mit Xephyr

Pakete:

- openSuSE (11.1): xorg-x11-server-extra

- CentOS (5.3): xorg-x11-server-Xephyr
- Debian (5.0): xserver-xephyr

```
Xephyr -query notebook17 :1 &
```

Links

- [Remote Desktop Client für RDP, VNC, NX, XDMCP und SSH](#)

Display-Manager auswählen

CentOS

/etc/sysconfig/desktop :

```
DISPLAYMANAGER=XDM
```

SuSE

/etc/sysconfig/displaymanager :

```
DISPLAYMANAGER=XDM
```

Debian

```
dpkg-reconfigure kdm
```

oder

/etc/X11/default-display-manager :

```
/usr/bin/kdm -query <server> :1 vt8
```

1)

Beim reload oder restart wird die xdm-Konfigurationsdatei angepasst:

/var/adm/kdm/kdmrc.sysconfig

```
[Xdmcp]  
Enable=true
```

From:

<https://wiki.lab.linuxhotel.de/> - **Linuxhotel Wiki**

Permanent link:

https://wiki.lab.linuxhotel.de/doku.php/admin_grundlagen:xdm?rev=1331804824

Last update: **2012/03/15 09:47**

